

- Press the **F8** key or click **Show Attributes and Methods** on the **Home** ribbon tab of the *Frame* into which you inserted an instance to show the *methods*, *read-only attributes*, and *attributes* of the selected [Instance \[general description\]](#).

To query the value of a *read-only attribute*, you might, for example, type:

```
print MyButton.UUID
```


Attributes of the Button

_Attributes of the Button

The *Button* provides:

- The *attributes* listed in the table of contents to the left.
- The [Attributes of All Objects](#).

To view all of the *methods*, *read-only attributes*, and *attributes* of the object, open the window [Show Attributes and Methods](#). The figure below illustrates the information using the example of the object *Station*.



Name	Value	Inherited	Watchable	Signature
MoveToFolderCtrl	VOID	✓		method
MTTR	0.0000			time
Name	"Station"	✓	*	string

Name of the attribute Current value of the attribute Data type of the assignment value

- Select **Show Attributes and Methods** on the context menu of the **Class Library** to show the *methods*, *read-only attributes*, and *attributes* of the selected [Class \[general description\]](#).
- Press the **F8** key or click **Show Attributes and Methods** on the **Home** ribbon tab of the *Frame* into which you inserted an instance to show the *methods*, *read-only attributes*, and *attributes* of the selected [Instance \[general description\]](#).

You can set the value of an attribute and you can get its value, either with the check boxes, the text boxes and drop-down lists in the dialog windows or by assigning values to the respective attributes.

- To **set the value** of an attribute, you might, for example, type:

```
MyButton.UseIcon := false
```

- To **get the value** of an attribute, you might, for example, type:

```
print MyButton.UseIcon  
posit := Station.Cont.XPos
```

Control [SimTalk] - Button

Sets the **Control**, which the *Button* designated by <Path> executes when you click it.

Remarks

The anonymous identifiers ? and @ are set to the *Button* when the method is called.

You can also enter a control which expects a *boolean* value as parameter. This control is called with the value `true` when you click the *Button* and with the value `false` when you release it.

The control is also called when you change the size of the *Button* or when you move it with Drag-and-Drop. If the control does not expect a parameter it will be called, as before, when you release the button.

Type

Attribute

Syntax

```
<Path>.Control:string
```

Assignment Value

You can assign a value of data type *string*.

Examples

```
MyButton.Control := "myControl"
```

```
self.~.~.&MyMethod.openDialog
```

ObjectHeight [SimTalk] - Button

Sets the **Height** of the *Button* designated by <Path> with which it is shown in the *Frame*.

Remarks

For an object height of more than 30 pixels the button shows the text of the label with a larger front size.

Type

Attribute

Syntax

```
<Path>.ObjectHeight:integer
```

Assignment Value

You can assign a value of data type *integer*.

Example

```
MyButton.ObjectHeight := 1 // meter
```

SimTalk

[Height \[text box\] - Button](#)

[ObjectWidth \[SimTalk\] - Button](#)

ObjectWidth [SimTalk] - Button

Sets the **Width** of the *Button* designated by <Path> with which it is shown in the *Frame*.

Remarks

If you enter a long label, you have to adjust the width so that the label fits on the button without the text being cut off.

Type

Attribute

Syntax

```
<Path>.ObjectWidth:integer
```

Assignment Value

You can assign a value of data type *integer*.

Example

```
MyButton.ObjectWidth := 4 // meters
```

SimTalk

[Width \[text box\] - Button](#)

[ObjectHeight \[SimTalk\] - Button](#)

DropDownList

DropDownList [object]

Use the object *DropDownList* for showing a drop-down list in the *Frame*. When you select one of the items, it executes the action which you programmed in the control.

Image

